


```
RRRRRRRR UU UU NN NN 000000 FFFFFFFF FFFFFFFF
RRRRRRRR UU UU NN NN 000000 FFFFFFFF FFFFFFFF
RR RR RR UU UU NN NN 00 00 FF FF
RR RR RR UU UU NN NN 00 00 FF FF
RR RR RR UU UU NNNN NN 00 00 FF FF
RRRRRRRR UU UU NN NN 00 00 FFFFFFFF FFFFFFFF
RRRRRRRR UU UU NN NN 00 00 FFFFFFFF FFFFFFFF
RR RR UU UU NN NN 00 00 FF
RR RR UU UU NN NN 00 00 FF
RR RR UU UU NN NN 00 00 FF
RR RR UU UU NN NN 00 00 FF
RR RR UU UU NN NN 00 00 FF
UUUUUUUUU NN NN 000000 FF
UUUUUUUUU NN NN 000000 FF
```

```
....
....
....
....
```

```
CCCCCCCC LL DDDDDDDD
CCCCCCCC LL DDDDDDDD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CC LL DD DD
CCCCCCCC LL DDDDDDDD
CCCCCCCC LL DDDDDDDD
```

Version: 'V04-000'

14 February 1984

Command-line description file for RUNOFF

define type contents_page_options

keyword running, negatable
keyword level, value(required, type=\$number)

define type index_page_options

keyword running, negatable

define syntax RUN_CONTENTS

image DSRTOC
parameter p1, label=input, prompt='File', value(required, list, type=\$infile)
qualifier bold
qualifier deepest_header, value(required, type=\$number), nonnegatable
qualifier identification
qualifier indent
qualifier log
qualifier output, value(type=\$outfile), default
qualifier page_numbers, value(required, list, type=contents_page_options), nonnegatable
qualifier require, value(required, type=\$infile)
qualifier section_numbers
qualifier underline

define syntax RUN_INDEX

image DSRINDEX
parameter p1, label=input, prompt='File', value(required, list, type=\$infile)
qualifier identification
qualifier lines_per_page, value(required, type=\$number), nonnegatable
qualifier log
qualifier output, value(type=\$outfile), default
qualifier page_numbers, value(list, type=index_page_options), default
qualifier require, value(required, type=\$infile)
qualifier reserve, value(required, type=\$number)

define type debug_options

keyword all, default
keyword conditionals
keyword contents
keyword files
keyword index

define type message_options

keyword output
keyword user

define verb RUNOFF

image RUNOFF
parameter p1, label=p1, prompt='File', value(required, list, type=\$infile)
qualifier backspace placement=positional, nonnegatable
qualifier bold, value(default=1, type=\$number), default, placement=positional
qualifier change_bars, value(default='f'), placement=positional
qualifier contents, syntax=run_contents

qualifier	debug,	value(list, type=debug_options, default=ALL), placement=positional
qualifier	dec_internal,	value(list), placement=positional, nonnegatable
qualifier	device,	value(required, list), placement=positional, nonnegatable
qualifier	down,	value(default=5, type=\$number), placement=positional
qualifier	form_size,	value(required, type=\$number), nonnegatable
qualifier	index,	syntax=run_index
qualifier	intermediate,	value(type=\$outfile), placement=positional
qualifier	log	
qualifier	messages,	value(required, type=message_options, list), placement=positional, nonnegatable
qualifier	output,	value(type=\$outfile), placement=positional
qualifier	overprint,	default, placement=positional, nonnegatable
qualifier	pages,	value(required), placement=positional, nonnegatable
qualifier	pause	
qualifier	right,	value(default=5, type=\$number), placement=positional
qualifier	sequence	placement=positional
qualifier	simulate	
qualifier	underline_character,	value(default=" "), default, placement=positional
qualifier	separate_underline,	value(default="="), placement=positional, nonnegatable
qualifier	nonspacing_underline,	value(default=""), placement=positional, nonnegatable
qualifier	variant,	value, placement=positional, nonnegatable

0046 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY